PrimeCell[®] Infrastructure AMBA[®] 3 AXI File Reader Master (BP144)

Revision: r0p0

Technical Overview



PrimeCell Infrastructure AMBA 3 AXI File Reader Master (BP144)

Technical Overview

Copyright © 2004 ARM Limited. All rights reserved.

Release Information

The following changes have been made to this book.

Change History

| Date | Issue | Change |
|------------------|-------|----------------------|
| 17 December 2004 | A | First issue for r0p0 |

Proprietary Notice

Words and logos marked with ® or ™ are registered trademarks or trademarks of ARM Limited in the EU and other countries, except as otherwise stated below in this proprietary notice. Other brands and names mentioned herein may be the trademarks of their respective owners.

Neither the whole nor any part of the information contained in, or the product described in, this document may be adapted or reproduced in any material form except with the prior written permission of the copyright holder.

The product described in this document is subject to continuous developments and improvements. All particulars of the product and its use contained in this document are given by ARM in good faith. However, all warranties implied or expressed, including but not limited to implied warranties of merchantability, or fitness for purpose, are excluded.

This document is intended only to assist the reader in the use of the product. ARM Limited shall not be liable for any loss or damage arising from the use of any information in this document, or any error or omission in such information, or any incorrect use of the product.

Where the term ARM is used it means "ARM or any of its subsidiaries as appropriate".

Confidentiality Status

This document is Non-Confidential. The right to use, copy and disclose this document may be subject to license restrictions in accordance with the terms of the agreement entered into by ARM and the party that ARM delivered this document to.

Product Status

The information in this document is final, that is for a developed product.

Web Address

http://www.arm.com

Contents

PrimeCell Infrastructure AMBA 3 AXI File Reader Master (BP144) Technical Overview

| Chapter 1 | nnical Overview | | |
|-----------|-----------------|------------------------|-----|
| - | 1.1 | About the AXI FRM | 1-2 |
| | 1.2 | Functional description | 1-3 |
| | 1.3 | Signal descriptions | 1-5 |

Contents

Chapter 1 **Technical Overview**

This technical overview describes the functionality of the AXI *File Reader Master* (FRM) in the following sections:

- About the AXI FRM on page 1-2
- Functional description on page 1-3
- Signal descriptions on page 1-5.

1.1 About the AXI FRM

You can use the AXI FRM, FileRdMasterAxi, to simulate AXI systems quickly and efficiently by generating explicit AXI bus transfers that are described in a stimulus file. It enables you to specify the requested timings of all master-generated signals.

The FRM supports a special command that enables the independent AXI channels to be synchronized at a point described in the stimulus file. It can also repeatedly read from an address until the data returned meets certain criteria.

The FRM is a behavioral component and is not intended to be synthesized.

The FileRdMasterAxi has the following features:

- It converts a human-readable stimulus file that describes transactions into AXI transfers.
- It comprises:
 - Perl pre-processor script
 - Verilog virtual component.
- It supports a subset of the AXI XVC vector format, see the *PrimeCell Infrastructure AMBA 3 AXI File Reader Master Design Manual*.
- It supports requested master generated timings.
- It supports a behavioral Quit command.
- It checks slave-generated data and responses.
- It has a configurable data bus width of 32 or 64 bits.

1.2 Functional description

Figure 1-1 shows the AXI FRM data flow.




Figure 1-1 FRM data flow

The stimulus input file is text-based. It enables you to define the AXI transactions for simulation. The filename of the stimulus data file is specified using a Verilog parameter at the point of instantiation within the HDL code.

The input stimulus file is converted to seven HDL hexadecimal format stimulus data files by the Perl pre-processor script:

- one for each AXI write channel:
 - write address
 - write data
 - write response.
- one for each AXI read channel:
 - read address
 - read data.
- one set of simulation comment vectors for each AXI address channel:
 - write address
 - read address.

The pre-processor script also checks the stimulus input file for syntax, functional errors and AXI protocol errors. The checks and errors are further described in the *PrimeCell Infrastructure AMBA 3 AXI File Reader Master Design Manual*.

The stimulus data files are input to the FRM. This initiates the defined transactions on the relevant AXI channels. The transactions are monitored by the FRM and compared with expected results from the stimulus data files. This comparison is output in the form of a human-readable transcript file.

1.2.1 Master interface attributes

Table 1-1 lists the FRM interface attributes.

Table 1-1 Master interface attributes

| Attribute | Description | Value |
|--------------------------|---|--------------------|
| Read ID capability | The maximum number of different ARID values that a master can generate for all active read transactions at any one time. | 1 |
| Read ID width | The number of bits in the ARID bus. | 0 |
| Read issuing capability | The maximum number of active read transactions that a master can generate. | Stimulus-dependent |
| Write ID capability | The maximum number of different AWID values that a master can generate for all active write transactions at any one time | 1 |
| Write ID width | The number of bits in the AWID and WID buses. | 0 |
| Write issuing capability | The maximum number of active write transactions that a master can generate. | Stimulus-dependent |

1.3 Signal descriptions

The AXI FRM uses standard AMBA AXI signals as described in the *AMBA AXI Protocol Specification* except for the following:

- AWID is not used and is not present on the write address channel interface
- WID is not used and is not present on the write data channel interface
- **BID** is not used and is not present on the write response channel interface
- ARID is not used and is not present on the read address channel interface
- **RID** is not used and is not present on the read data channel interface
- **RLAST** is not used but is present on the read data channel interface.

The AXI FRM signals are shown in:

- Global and low-power interface signals
- Write channel signals
- Read channel signals on page 1-6.

----- Note ------

The upper value of some bus widths is provided as a name to indicate that the number of signal lines in the bus is derived from user-defined generics or parameters. These are described in the *PrimeCell Infrastructure AMBA 3 AXI File Reader Master Design Manual*.

1.3.1 Global and low-power interface signals

Figure 1-2 shows the AXI global and low-power interface signal connections.



Figure 1-2 Global and low-power interface signal connections

1.3.2 Write channel signals

Figure 1-3 on page 1-6 shows the AXI write address, write data, and write response channel signal connections




Figure 1-3 Write channel signal connections

1.3.3 Read channel signals

Figure 1-4 shows the AXI read address and read data channel signal connections.




Figure 1-4 Read channel signal connections