



# Image Classification with MobilenetV2, Arm NN, and TensorFlow Lite Delegate pre-built binaries

Version 21.11

## Tutorial

### Non-Confidential

Copyright © 2021 Arm Limited (or its affiliates).  
All rights reserved.

### Issue 01

102561\_2111\_01\_en



# Image Classification with MobilenetV2, Arm NN, and TensorFlow Lite Delegate pre-built binaries

## Tutorial

Copyright © 2021 Arm Limited (or its affiliates). All rights reserved.

## Release information

### Document history

Issue	Date	Confidentiality	Change
0100-01	21 July 2021	Non-Confidential	First release for version 1.01
2108-01	17 August 2021	Non-Confidential	First release for version 21.08
2108-02	18 October 2021	Non-Confidential	Second release for version 21.08
2111-01	22 November 2021	Non-Confidential	First release for version 21.11

## Proprietary Notice

This document is protected by copyright and other related rights and the practice or implementation of the information contained in this document may be protected by one or more patents or pending patent applications. No part of this document may be reproduced in any form by any means without the express prior written permission of Arm. No license, express or implied, by estoppel or otherwise to any intellectual property rights is granted by this document unless specifically stated.

Your access to the information in this document is conditional upon your acceptance that you will not use or permit others to use the information for the purposes of determining whether implementations infringe any third party patents.

THIS DOCUMENT IS PROVIDED "AS IS". ARM PROVIDES NO REPRESENTATIONS AND NO WARRANTIES, EXPRESS, IMPLIED OR STATUTORY, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY, SATISFACTORY QUALITY, NON-INFRINGEMENT OR FITNESS FOR A PARTICULAR PURPOSE WITH RESPECT TO THE DOCUMENT. For the avoidance of doubt, Arm makes no representation with respect to, and has undertaken no analysis to identify or understand the scope and content of, third party patents, copyrights, trade secrets, or other rights.

This document may include technical inaccuracies or typographical errors.

TO THE EXTENT NOT PROHIBITED BY LAW, IN NO EVENT WILL ARM BE LIABLE FOR ANY DAMAGES, INCLUDING WITHOUT LIMITATION ANY DIRECT, INDIRECT, SPECIAL, INCIDENTAL, PUNITIVE, OR CONSEQUENTIAL DAMAGES, HOWEVER CAUSED AND

REGARDLESS OF THE THEORY OF LIABILITY, ARISING OUT OF ANY USE OF THIS DOCUMENT, EVEN IF ARM HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

This document consists solely of commercial items. You shall be responsible for ensuring that any use, duplication or disclosure of this document complies fully with any relevant export laws and regulations to assure that this document or any portion thereof is not exported, directly or indirectly, in violation of such export laws. Use of the word “partner” in reference to Arm’s customers is not intended to create or refer to any partnership relationship with any other company. Arm may make changes to this document at any time and without notice.

If any of the provisions contained in these terms conflict with any of the provisions of any click through or signed written agreement covering this document with Arm, then the click through or signed written agreement prevails over and supersedes the conflicting provisions of these terms. This document may be translated into other languages for convenience, and you agree that if there is any conflict between the English version of this document and any translation, the terms of the English version of the Agreement shall prevail.

The Arm corporate logo and words marked with ® or ™ are registered trademarks or trademarks of Arm Limited (or its subsidiaries) in the US and/or elsewhere. All rights reserved. Other brands and names mentioned in this document may be the trademarks of their respective owners. Please follow Arm’s trademark usage guidelines at <https://www.arm.com/company/policies/trademarks>.

Copyright © 2021 Arm Limited (or its affiliates). All rights reserved.

Arm Limited. Company 02557590 registered in England.

110 Fulbourn Road, Cambridge, England CB1 9NJ.

(LES-PRE-20349)

## Confidentiality Status

This document is Non-Confidential. The right to use, copy and disclose this document may be subject to license restrictions in accordance with the terms of the agreement entered into by Arm and the party that Arm delivered this document to.

Unrestricted Access is an Arm internal classification.

## Product Status

The information in this document is Final, that is for a developed product.

## Web address

[developer.arm.com](https://developer.arm.com)

## Inclusive language commitment

Arm values inclusive communities. Arm recognizes that we and our industry have used language that can be offensive. Arm strives to lead the industry and create change.

We believe that this document contains no offensive language. To report offensive language in this document, email [terms@arm.com](mailto:terms@arm.com).

# Contents

<b>1 Introduction.....</b>	<b>6</b>
1.1 Conventions.....	6
1.2 Additional reading.....	7
1.3 Feedback.....	7
1.4 Other information.....	8
<b>2 Overview.....</b>	<b>9</b>
2.1 Before you begin.....	9
2.2 Arm NN TensorFlow Lite Delegate.....	9
2.3 Image classification.....	9
<b>3 Device-specific installation.....</b>	<b>11</b>
3.1 Install on Raspberry Pi.....	11
3.2 Install on Odroid N2 Plus.....	12
<b>4 Overview of running the application.....</b>	<b>14</b>
4.1 Run the application.....	14
<b>5 Code deep dive.....</b>	<b>16</b>
5.1 Build the application.....	16
<b>6 Related information.....</b>	<b>20</b>
<b>7 Next steps.....</b>	<b>21</b>
<b>A Revisions.....</b>	<b>22</b>

# 1 Introduction

## 1.1 Conventions

The following subsections describe conventions used in Arm documents.




### Glossary




The Arm Glossary is a list of terms used in Arm documentation, together with definitions for those terms. The Arm Glossary does not contain terms that are industry standard unless the Arm meaning differs from the generally accepted meaning.

See the Arm® Glossary for more information: [developer.arm.com/glossary](https://developer.arm.com/glossary).

### Typographic conventions

Arm documentation uses typographical conventions to convey specific meaning.

Convention	Use
<i>italic</i>	Introduces special terminology, denotes cross-references, and citations.
<b>bold</b>	Highlights interface elements, such as menu names. Denotes signal names. Also used for terms in descriptive lists, where appropriate.
monospace	Denotes text that you can enter at the keyboard, such as commands, file and program names, and source code.
<i>monospace italic</i>	Denotes arguments to monospace text where the argument is to be replaced by a specific value.
<b>monospace bold</b>	Denotes language keywords when used outside example code.
monospace <u>underline</u>	Denotes a permitted abbreviation for a command or option. You can enter the underlined text instead of the full command or option name.
<and>	Encloses replaceable terms for assembler syntax where they appear in code or code fragments. For example: <pre>MRC p15, 0, &lt;Rd&gt;, &lt;CRn&gt;, &lt;CRm&gt;, &lt;Opcode_2&gt;</pre>
<b>SMALL CAPITALS</b>	Used in body text for a few terms that have specific technical meanings, that are defined in the <i>Arm Glossary</i> . For example, <b>IMPLEMENTATION DEFINED</b> , <b>IMPLEMENTATION SPECIFIC</b> , <b>UNKNOWN</b> , and <b>UNPREDICTABLE</b> .
 Caution	This represents a recommendation which, if not followed, might lead to system failure or damage.
 Warning	This represents a requirement for the system that, if not followed, might result in system failure or damage.
 Danger	This represents a requirement for the system that, if not followed, will result in system failure or damage.

Convention	Use
 Note	This represents an important piece of information that needs your attention.
 Tip	This represents a useful tip that might make it easier, better or faster to perform a task.
 Remember	This is a reminder of something important that relates to the information you are reading.

## 1.2 Additional reading

This document contains information that is specific to this product. See the following documents for other relevant information:

**Table 1-2: Arm publications**

Document Name	Document ID	Licensee only
None	-	-

## 1.3 Feedback

Arm welcomes feedback on this product and its documentation.

### Feedback on this product

If you have any comments or suggestions about this product, contact your supplier and give:

- The product name.
- The product revision or version.
- An explanation with as much information as you can provide. Include symptoms and diagnostic procedures if appropriate.

### Feedback on content

If you have comments on content then send an e-mail to [errata@arm.com](mailto:errata@arm.com). Give:

- The title Image Classification with MobilenetV2, Arm NN, and TensorFlow Lite Delegate pre-built binaries Tutorial.
- The number 102561\_2111\_01\_en.
- If applicable, the page number(s) to which your comments refer.
- A concise explanation of your comments.

Arm also welcomes general suggestions for additions and improvements.



Arm tests the PDF only in Adobe Acrobat and Acrobat Reader, and cannot guarantee the quality of the represented document when used with any other PDF reader.

---

## 1.4 Other information

See the Arm website for other relevant information.

- [Arm® Developer](#).
- [Arm® Documentation](#).
- [Technical Support](#).
- [Arm® Glossary](#).



## 2 Overview

This guide reviews a sample application for image classification using the Arm NN TensorFlow Lite Delegate (Arm NN TfLite Delegate). The guide explains how to build the application and deploy it onto your device and goes into a code deep dive.

This guide is suitable for both beginners and experienced developers. We can use the early sections of the guide to get an app up and running in minutes. For more experienced developers, we also go further into detail later in the guide in the [Code deep dive](#) section.

### 2.1 Before you begin

This guide requires installing the Arm NN TfLite Delegate on your device. In this guide, we show steps on how to use our pre-built binaries available on GitHub. To use these binaries, you require a 64-bit Arm device.

We provide installation steps for different devices in the [Device-specific installation](#) section.

### 2.2 Arm NN TensorFlow Lite Delegate

The Arm NN TfLite Delegate is the latest addition to the Arm NN library. It is a library for accelerating certain TensorFlow Lite (TfLite) operators on Arm hardware. The Arm NN TfLite Delegate uses the delegate system of TfLite delegate system. As a result, TfLite delegates any operations Arm NN supports to Arm NN during execution.

There are two advantages of using the Arm NN TfLite Delegate over the Arm NN TfLite Parser.

The first advantage is that the number of supported operations is far greater. The Arm NN TfLite Parser only supports a model if Arm NN supports all operations in the model. Conversely when using the Arm NN TfLite Delegate, any operations not supported by Arm NN are delegated to TensorFlow Lite. This delegation means Arm NN TfLite Delegate can execute all TfLite models, and accelerates any operations that Arm NN supports.

The second advantage is that the Arm NN TfLite Delegate can be easily integrated into your Python TfLite projects. Arm NN TfLite Delegate only requires an extra line to load the delegate into the interpreter.

### 2.3 Image classification

Image classification is one of the most popular deep learning problems. Because of the vast number of datasets available, neural networks have been able to excel in this field.

There have also been many advancements for edge devices. One key model is the MobileNet architecture. This architecture uses depth-wise separable convolution layers to create a lightweight image classification model that performs efficiently on mobile and embedded devices.

This guide shows how to use one of the latest versions of MobileNet, MobileNetv2, with the Arm NN TfLite Delegate.

## 3 Device-specific installation

The easiest way to get started with the Arm NN Tflite Delegate on your device is using the pre-built binaries in the Arm NN repository. We provide pre-built binaries for 64-bit Arm devices and Android devices.

### 3.1 Install on Raspberry Pi

The steps in this section cover installing the Arm NN Tflite Delegate on the Raspberry Pi.

#### Procedure

1. Install Ubuntu. See installation instructions for the [Raspberry Pi4 on the Ubuntu website](#). This guide has been tested on 64-bit versions of Ubuntu 20.04 and Ubuntu 21.04.
2. Run the `apt update` and `apt upgrade` commands. When on a fresh installation, it is best practice to run these commands. This step ensures all packages are the latest versions. Enter the following commands:

```
sudo apt update
sudo apt upgrade
```

3. Install the required packages that build and install the TensorFlow Lite runtime with Arm NN support. To install the packages, enter the following commands:

```
sudo apt-get install git wget unzip zip python cmake scons openjdk-11-jdk python3
python3-pip
```

4. Set a base directory variable to refer to. To set the base directory, enter the following command:

```
export BASEDIR=$(pwd)
```

5. Install the TensorFlow Lite runtime package from source. To install the package, enter the following commands:

```
pip3 install --extra-index-url https://google-coral.github.io/py-repo/
tflite_runtime
```

6. Download the pre-built binaries for Arm NN 21.11 for 64-bit Arm systems. The following commands download version 21.11 of the Arm NN binaries and place them into a directory called ArmNN-aarch64:

```
wget -O ArmNN-aarch64.tgz https://github.com/ARM-software/armnn/releases/download/v21.11/ArmNN-linux-aarch64.tar.gz
mkdir ArmNN-aarch64
tar -xvf ArmNN-aarch64.tgz -C ArmNN-aarch64 --strip-components 1
```

## 3.2 Install on Odroid N2 Plus

The steps in this section cover installing the Arm NN Tflite Delegate on the Odroid N2 Plus.

### About this task

Odroid lists many official Linux releases available on the Odroid wiki. This guide covers testing the Odroid N2 Plus on the Ubuntu MATE 20.04 image. In addition to an Arm Cortex-A CPU, the Odroid N2 Plus has an Arm Mali GPU. This installation includes installing the required packages to allow the Arm NN Delegate to take advantage of the GPU.



If you struggle with memory errors on the Odroid N2 Plus in step nine, edit `build_pip_package_with_bazel.sh` to limit Bazel to use only four jobs using the option `--jobs=4`. Making this change can help the build system work more efficiently.

### Procedure

1. Install the Ubuntu MATE 20.04 image.
2. Run the `apt update` and `apt upgrade` commands. When on a fresh installation, it is best practice to run these commands. This step ensures all packages are the latest versions. Enter the following commands:

```
sudo apt update
sudo apt -y upgrade
```

3. Install the OpenCL package for GPU support. To install the package, enter the following command:

```
sudo apt-get install -y ocl-icd-opencl-dev
sudo mkdir -p /etc/OpenCL/vendors/
sudo bash -c 'echo "libmali.so" > /etc/OpenCL/vendors/mali.icd'
```

4. Install the required packages to build and install TensorFlow Lite runtime with Arm NN support. To install the packages, enter the following commands:

```
sudo apt-get install git wget unzip zip python git-lfs cmake scons openjdk-11-jdk
python3 python3-pip
```

5. Set a base directory variable to refer to. To set a base directory variable, enter the following command:

```
export BASEDIR=$(pwd)
```

6. Install the TensorFlow Lite runtime package from source. To install the package, enter the following commands:

```
pip3 install --extra-index-url https://google-coral.github.io/py-repo/
tflite_runtime
```

7. Download the pre-built binaries for Arm NN 21.11 for 64-bit Arm systems. The following commands download version 21.11 of the Arm NN binaries and place them into a directory called `ArmNN-aarch64`:

```
wget -O ArmNN-aarch64.tgz https://github.com/ARM-software/armnn/releases/download/v21.11/ArmNN-linux-aarch64.tar.gz
```

```
mkdir ArmNN-aarch64  
tar -xvf ArmNN-aarch64.tgz -C ArmNN-aarch64 --strip-components 1
```

## 4 Overview of running the application

This section includes the steps to run the application on your device.

This section covers the following:

- Downloading the sample application.
- Copying your `libtensorflow_lite_all.so` and `libarmnn.so` libraries into the example folder.
- Downloading a model and the corresponding label-mapping file.
- Downloading a sample image to use in the model.
- Installing the required Python packages.

### 4.1 Run the application

The steps in this section cover running the application on your device.

#### Before you begin

Before following the instructions in this section, ensure you follow the installation steps and have built and downloaded both `libarmnnDelegate.so` and `libtensorflow_lite_all.so`. Also, ensure you have installed the `tf-lite-runtime` Python package from source.

#### Procedure

1. Download the sample application. The application is inside the Arm NN repository in the `samples` folder. Perform a `git clone` on the Arm NN repository and change into the example folder. To perform a `git clone` and change into the example folder, enter the following commands:

```
git clone https://github.com/arm-software/armnn
cd armnn/samples/ImageClassification
```

2. Copy over the `libarmnn.so` and `libarmnnDelegate.so` libraries into the example folder. To copy these libraries, enter the following commands:

```
cp $BASEDIR/ArmNN-aarch64/libarmnn.so.27 .
cp $BASEDIR/ArmNN-aarch64/libarmnnDelegate.so.25 .
```

3. Download a model and the corresponding label-mapping file. In this application, we use the MobilenetV2 model. An optimized version of this model can be found in the Arm Model Zoo on GitHub.

```
export EXAMPLEDIR=$(pwd)
git clone https://github.com/arm-software/ml-zoo.git
# generate the label mapping
cd ml-zoo/models/image_classification/mobilenet_v2_1.0_224/tflite_uint8
./get_class_labels.sh
cd $EXAMPLEDIR
cp ml-zoo/models/image_classification/mobilenet_v2_1.0_224/tflite_uint8/mo\
bilenet_v2_1.0_224_quantized_1_default_1.tflite .
```

```
cp ml-zoo/models/image_classification/mobilenet_v2_1.0_224/tflite_uint8/labelmap\
pings.txt .
```

You can also use your own model if it satisfies the following requirements:

- It has been converted to the `.tflite` format.
  - It expects an image input of either greyscale or RGB.
  - It outputs a single vector containing probabilistic predictions for each class.
  - You have the label-mapping file which converts the output vector index to a class label.
4. Download a sample image to use in the model. To download a sample image, enter the following command:

```
wget -O cat.png "https://github.com/dmlc/mxnet.js/blob/main/data/cat.p\
ng?raw=true"
```

5. Install the required Python packages. You must have followed the steps in the [Device-specific installation](#) section and installed `tflite_runtime` to perform this step. To install the Python packages you require, enter the following command:

```
pip3 install -r requirements.txt
```

6. Run the `run_classifier.py` application. You are ready to run this application. To run the application, we provide a command-line interface which allows you to pass in your model, your label mapping, the Arm NN backends, your input image, and the location of your delegate. The following is example usage for a device with an Arm CPU and GPU:

```
python3 run_classifier.py \
--input_image cat.png \
--model_file mobilenet_v2_1.0_224_quantized_1_default_1.tflite \
--label_file labelmappings.txt \
--delegate_path $BASEDIR/ArmNN-aarch64/libarmnnDelegate.so.24 \
--preferred_backends GpuAcc CpuAcc CpuRef
```

To see all available options with information about their use, you can use the command `python3 run_classifier.py -h`.

## 5 Code deep dive

In this section of the guide, we take a deep dive into the code we use in the application by building the application ourselves from scratch.

The Arm NN TFLite Delegate integrates with the TFLite package. If you are familiar with TFLite, using the delegate only adds an extra line of code to your projects. If you are not familiar with TFLite, there are many TensorFlow tutorials, guides, and sample applications online you can use to learn more.

An image classification application performs the following steps:

- Load the model.
- Load the input image.
- Load the label-mapping files.
- Resize the image to fit with the models expected input size.
- Run the inference engine.
- Calculate which output neuron has the highest output value. The highest output value represents the highest probability.
- Convert the index of the neuron to a label-mapping file.

### 5.1 Build the application

The following steps allow you to follow along with the code deep dive and build the application.

#### Procedure

1. Import the dependencies and create a command-line interface with `argparse`. We rely on the following external dependencies: Pillow, a package to help with image processing; Numpy, a package used to store and modify arrays; and the TensorFlow Lite runtime package. For the command-line interface, we add options that allow you to input the following:
  - An input image.
  - A model.
  - A label mapping.
  - The location of the delegate library.
  - The backends Arm NN uses.

```
import argparse
from pathlib import Path
from typing import Union
import tflite_runtime.interpreter as tflite
from PIL import Image
import numpy as np

parser = argparse.ArgumentParser(
    formatter_class=argparse.ArgumentDefaultsHelpFormatter
```



```
)
parser.add_argument(
    '--input_image', help='File path of image file', type=Path,
    required=True
)
parser.add_argument(
    '--model_file', help='File path of the model tflite file', type=Path,
    required=True
)
parser.add_argument(
    '--label_file', help='File path of model labelmapping file', type=Path,
    required=True
)
parser.add_argument(
    '--delegate_path', help='File path of ArmNN delegate file', type=Path,
    required=True
)
parser.add_argument(
    '--preferred_backends', help='list of backends in order of preference',
    type=str, nargs='+', required=False, default=["CpuAcc", "CpuRef"]
)
args = parser.parse_args()
```

2. Load the `tflite` model file. Compared to a normal TensorFlow Lite application, we add one or two extra lines to import the Arm NN delegate.

Use the `load_delegate()` function from `tflite`. This function takes as input the path of the delegate and the options for the delegate, given in a Python dictionary format. For the Arm NN Delegate, the main option is the `backends` option. On this option, you input the backends available on your device or Arm NN installation.

The backend option is in string format. For example: `GpuAcc,CpuAcc,CpuRef`.

Use the `tflite` `Interpreter` class. For this class, pass the model file path as an input and add a section option of `experimental_delegates`. In this input, we pass the Arm NN delegate. This input tells the interpreter to offload calculations to the delegate.

The following example code loads the `tflite` model file:

```
delegate_path = args.delegate_path
model_path = args.model_file
backends = args.preferred_backends
backends = ",".join(backends)
#load the delegate
armnn_delegate = tflite.load_delegate(delegate_path,
options={
    "backends": backends,
    "logging-severity": "info"
})
#load the model and delegate to the interpreter
interpreter = tflite.Interpreter(
    model_path=model_path.as_posix(),
    experimental_delegates=[armnn_delegate]
)
```

3. Load the label-mapping files. You must convert the output into an understandable format. When a neural network model is being trained, we assign each class an output neuron. Label-mapping files take the output from a neural network and convert it back to a class. This output usually comes in the form of a text file where each row has a class name. Usually, the row

number refers to the index of an output neuron. Also, both the row number and the index of the output neuron usually start at zero.

For this reason, when loading the label-mapping files it is a good idea for it to be in a Python dictionary. Loading the label-mapping files this way makes it easy to query the class label from the output of a neural network.

The following example code loads the label-mapping files:

```
label_mapping_p = args.label_file
idx = 0
label_mapping = {}
with open(label_mapping_p) as label_mapping_raw:
    for line in label_mapping_raw:
        label_mapping[idx] = line
        idx += 1
```

4. Load the input image. The input image must be of a specific size and format. A common format is 224 x 224 x 3. This format means a height of 224 pixels, a width of 224 pixels, and three channels of red, green, and blue. You can find out the expected input format for the model from the interpreter you created previously. Using this input format, you can process your image.

The following example code loads the input image:

```
input_details = interpreter.get_input_details()
input_shape = input_details[0]['shape']
#batch size = input_shape[0], this can be ignored here. We will only be using 1
img.
height, width, channels = input_shape[1], input_shape[2], input_shape[3]
#if channels == 1 then greyscale
greyscale = channels == 1
#load the input image
image_path = args.input_image
image = Image.open(image_path).resize((width, height))
if greyscale:
    image = image.convert("LA")
#extend dims so model can expect it.
image = np.expand_dims(image, axis=0)
```

5. Run the inference engine. You must allocate the tensors, assign the input image to the input tensor, and run the inference. The following example code runs the inference engine:

```
interpreter.allocate_tensors()
input_details = interpreter.get_input_details()
output_details = interpreter.get_output_details()
interpreter.set_tensor(input_details[0]['index'], image)
interpreter.invoke()
output_data = interpreter.get_tensor(output_details[0]['index'])
```

6. Process the output data. To process the output data, you calculate the largest output value. The largest output represents the highest probability, so by taking the largest value you get the value the model believes is most likely. The following example code calculates the largest output value:

```
output_index = np.argmax(output_data[0])
```

7. Calculate the class label. You can query the dictionary you made earlier for class labels with the output index you calculated. The following example code calculates the class label:

```
output_class = label_mapping[output_index]
```

```
print("Predicted class: ", output_class)
```

## 6 Related information

Here are some resources related to the material in this guide:

- [Odroid N2+](#)
- [Odroid Wiki](#)
- [Raspberry Pi 4](#)
- [TensorFlow Lite](#)

Other Arm resources:

- [Arm Community](#) - ask development questions and find articles and blogs on specific topics from Arm experts.
- [Arm NN Github](#) - raise queries or issues associated with the Arm NN how-to guides.
- [Arm NN Product Documentation](#) - find out more about the latest Arm NN features.

## 7 Next steps

This guide covers the steps to develop an image classification application using the quantized TensorFlow Lite MobileNet V2 model. This model is available in the Arm ML-Zoo and the Arm NN TensorFlow Lite Delegate. You can use the example code in this application as a starting point for your own image classification applications.

You can also have a look at how the MobileNet V2 model was trained and train your own using the [TensorFlow Slim GitHub repository](#).

For application inspiration, why not look at our [fire detection use case](#) which uses image classification to detect fires?

# Appendix A Revisions

This appendix describes the technical changes between released issues of this book.

**Table A-1: First release for version 1.01**

Change	Location
First release	—

**Table A-2: First release for version 21.08**

Change	Location
Updates steps	<a href="#">Install on Odroid N2 Plus</a>
Updates steps	<a href="#">Run the application</a>
Adds additional resources	<a href="#">Related information</a>

**Table A-3: Second release for version 21.08**

Change	Location
Adds additional resources	<a href="#">Related information</a>
Fixes typo	<a href="#">Install on Odroid N2 Plus</a>

**Table A-4: First release for version 21.11**

Change	Location
Updates the Odroid N2 Plus installation instructions	<a href="#">Install on Odroid N2 Plus</a>
Updates the Raspberry Pi installation instructions	<a href="#">Install on Raspberry Pi</a>
Updates library version numbers and removes non-inclusive language	<a href="#">Run the application</a>